

## Integrating BioBridge SDK with C# (ActiveX)

1. Select the Windows Application and click OK.

Project types:		<u>T</u> emplates:		
Visual Basic     Windows     Starter Kits     Visual C#     Other Project Types		Visual Studio installed templa Windows Application Windows Control Library My Templates	ites	
A project for crea	ating an application v	vith a Windows user interface		
A project for crea	ating an application v WindowsApplicat	vith a Windows user interface		
A project for crea Name: Location:	ating an application v WindowsApplicat C:\Documents ar	vith a Windows user interface ion2 nd Settings\Administrator\My Documents\	biobridge	Browse

2. Go to Project -> Add References

🤣 WindowsApplication2 - Microsoft Visual Studio		- 8 🛛
Elle     Edit     Yiew     Project     Build     Debug     Data     Tools       Image: Im	Window Community Help Debug Any CPU · 2020 한 만 참 참 참 하 다 다 다 다 다, 막, 명 말 문	· · · · · · · · · · · · · · · · · · ·
Toolbox     Image: Construction of the sector	Object Browser	× X Solution Explorer - Solution ↓ ↓     Solution WindowsApplication2' (1
General Add Wgb Reference Set as StartUp Project Controls in this groi Drag an item onto C WindowsApplication2 Properties text to add it to the toolbox.		Solution Explorer @gclass View
G Server E X Toobox	o	Properties 4 X Form1.cs File Properties 4 Advanced Build Action Compile Copy to Output Do not copy Custom Tool
Output Show output from:	4 4   <del>3</del>   <b>2</b>	A     A     Custom Tool Ne     Misc     File Name Form1.cs     Full Path C:\Documents and
Trine liel 🗐 Quitruit		Advanced



3. Click the Browse Tab and locate the "BioBridge SDK" file. It is normally located at C\windows\system32\ BioBridgeSDK.ocx

		?
NET COM	Projects Browse Recent	
Look in: 🦳	WindoweApplication?	
		_
🛄 obj		
Properties		
File name:	<u></u>	
File <u>n</u> ame:		~

Look jn: 📔	) system32	💌 😋 🏚 📂 🖽 •
🔊 azroles.dll		BioBridgeSDK.ocx
🔊 basecsp.d		🔊 biokey.ocx
🔊 basesrv.d	II.	🔊 bitsprx2.dll
🔊 batmeter.	dll	🔊 bitsprx3.dll
🔊 batt.dll		🔊 bitsprx4.dll
🔊 bosprsrc.o	11	🔊 blackbox.dll
🔊 bidispl.dll		🛅 blastcin.exe
🔊 bio0.ocx		mbootcfg.exe
<		Description: Boot Cor
File <u>n</u> ame:	BioBridgeSDK.ocx	File Version: 5.1.260
Files of horses	Component Eiles (* dll.* Mb.* of	Size: 139 KB





4. Now, go to the General tab on the left hand side and right click to select "Choose Items".

5. Select "COM Components" Tab and select BioBridgeSDK control.

NET Framework Components COM C	mponents		
Name	Path	Library	1
<ul> <li>ActiveSkin 4.3 Control</li> <li>adbanner Class</li> <li>AFXOnlineMain Control</li> <li>Ahixib class</li> </ul>	C:\WINDOW5\system32\act: C:\WINDOW5\system32\msc C:\WINDOW5\system32\ZKC C:\WINDOW5\system32\inet	skn43.ocx ActiveSkin 4.3 T. Jxm.ocx Online.ocx Biokey Online(1:M srv\cert tom	 1)
BioBridgeSDK Control     Chilkat Ftp2     COMNSView Class	C:\Program Files\FingerTec\1 C:\WINDOWS\system32\chill C:\WINDOWS\system32\com	CMSv2\ BioBridgeSDK A katftp2.dll Chilkat Ftp2 2.0.1 isnap.dll ComSnap 1.0 T	)
Crystal Report Control     Crystal Report Viewer Control     CTreeView Control	C:\WINDOW5\system32\Cry C:\WINDOW5\system32\crvi C:\WINDOW5\system32\dma	stl32.ocx Crystal Report ewer.dll Crystal Report ocx.dll ctv OLE Control	
< <u> </u>	ш. Ш		>
BioBridge5DK Control Language: Language Neu Version: 1.0	ral	Brows	se



6. The BioBridge SDK component has been added to your project and now you can start using its functions.

